

Reminder: AOL will never ask you to send us your password or credit card number in an email.

This message has been scanned for known viruses.

From: Dave C.

To: lgreg1@aol.com

Subject: Entourage Set-up


Date: Mon, 12 Jun 2006 14:16:36 -0700

Setting Up Your E-mail in Microsoft Entourage


This tutorial shows you how to set up Microsoft Entourage to work with your e-mail account. This tutorial focuses on setting up Microsoft Entourage 2003, but these settings are similar in other versions of Microsoft Entourage. You can set up previous versions of Microsoft Entourage by using the settings in this tutorial.

To Set Up Your E-mail Account in Microsoft Entourage


1. Open Microsoft Entourage 2004.
2. Select Tools > Accounts.




3. Click "New."



4. If the "Account Setup Assistant" window displays, click "Configure account manually."



5. Select POP for the account type and click OK.



6. On the Edit Account window, enter your information as follows:

Account name

Enter a name for your account, for example: My Mail, Work, or Home.

Name

Enter your first and last name.

E-mail address

Enter your e-mail address.

Account ID

Enter your e-mail address, again.

POP server

Your incoming server is `mail.coolexample.com`, where "coolexample.com" is the name of your domain.

Password

Enter the password for your e-mail account.

SMTP server

Enter `smtpout.secureserver.net` for your outgoing mail server.

Click "[Click here for more advanced sending options.](#)"

NOTE: "smtpout.secureserver.net" is an SMTP relay server. In order to use this server to send e-mails, you must first activate SMTP relay on your e-mail account. Log on to your Manage Email Accounts page to set up SMTP relay. If you do not have SMTP relay set up and your Internet Service Provider (ISP) allows it, you can use the outgoing mail server for your Internet Service Provider. Contact your Internet Service Provider to get this setting.

7. Select "Override default SMTP port" and change the number to 80.
8. Select "SMTP server requires authentication" and "Use same settings as receiving mail server ." Click OK.

Sincerely yours,

Dave C.
Team Coral
Customer Care Center